

# SolidView Network Installation Guide

## Operating System Requirements:

Windows 2003 Server, Windows XP, Windows Vista or Windows 7

## Server Installation:

1. Download and install the SolidView Network Server Tool\* directly from the SolidView website: <https://www.solidview.com/Support/Download>
2. Launch the SolidView Network Server Tool via  
→ Start | Programs | Solid Concepts | License Administration Utility and select → [Activate Online]
3. Enter your activation codes which you obtained from your purchase confirmation email.
4. Press the [ok] button to complete the server install.

## Client Installation:

1. Download and install SolidView/Pro or SolidView/Pro RP (depending on which version you purchased) directly from the SolidView website: <http://www.solidview.com/Support/Download>
2. Launch the application and select the [Use License Server] checkbox in the "Please Activate SolidView" window.
3. Enter the name of the server computer and leave the port number as 2375.
4. Re-start SolidView to complete the client install.

\* The SolidView Network Server Tool was created using the RLM license manager obtained from Reprise ([www.reprisesoftware.com](http://www.reprisesoftware.com)).

## License Server Administration:

Open Internet Explorer to: <http://<servername>:5054/home.asp>  
(or <http://<servername>:9000/home.asp> if you are accessing it from the server machine).

Here you can restart the license server via the [Reread/Restart Server] button and check the SolidView license usage via the [Status] button.

## Example:

The screenshot shows a web browser window titled "rlm admin - Reprise License Server Administration - Microsoft Internet Explorer provided by Solid Concepts Inc." with the address bar showing "http://svserver01:5054/home.asp". The browser's taskbar includes icons for SolidView Web Viewer, FtpIn, FtpOut, SC Webmail, IT Support, SCI Intranet, Spam Management, Web Slice Gallery, Webmail, and Ticketing System Log. The web page has a green header with the title "Reprise License Server Administration" and the copyright notice "Copyright (c) 2006-2007, Reprise Software, Inc. All Rights Reserved." Below the header, the page is titled "RLM License Server Administration, v6.0" and states "This web interface is an integral part of the rlm server." It provides instructions: "If rlm is started without any parameters, the web interface runs on port 9000. rlm can also be started with the -nows option to disable this web interface. rlm can be started with the -ws port# option to specify another port number." It also notes: "This tool allows you to perform status and administration functions on the RLM server. Choose a command from the list on the left-hand side of the window." On the left side, there is a sidebar titled "RLM Administration Commands" with a list of buttons: "Status", "Shutdown", "Reread/Restart Servers", "Switch Reportlog", "New Reportlog", "Switch Debuglog", "Activate License", "RLM Manual...", "System Info", and "About...". On the right side, there is contact information for Reprise Software, Inc. (1530 Meridian Ave, Suite 290, San Jose, CA 95125, www.reprisesoftware.com, info@reprisesoftware.com), a note about OpenSSL software, and a "goahead WEB SERVER" logo.