

# SolidView Network Installation Guide

## Operating System Requirements:

Windows 2008 Server, and Windows 10

## License File Request:

1. Download and install the SolidView Network Server Tool\* directly from the SolidView website:  
*<https://www.solidview.com/Support/Download>*
2. Launch the SolidView Network Server Tool via  
Start > Programs > Stratasys Direct Manufacturing > License Administration Utility and select → [Activate Online]
3. Select → [I don't have an Activation Key]
4. Enter your name, phone number, email, serial number, and then select → [Submit]
5. A license file will then be created and sent to the email you attached.

## Server Installation:

1. Once you receive the License File, save it to your computer.
2. Launch the SolidView Network Server Tool via  
Start > Programs > Stratasys Direct Manufacturing > License Administration Utility and Select → [Read License File...]
3. When it prompts to restart the server, select → [Yes]
4. You have now completed the server install.

## Client Installation:

1. Download and install SolidView/Pro or SolidView/Pro RP (depending on which version you purchased) directly from the SolidView website: <http://www.solidview.com/Support/Download>
2. Launch the application and select the [Use License Server] checkbox in the "Please Activate SolidView" window.
3. Enter the name of the server computer and leave the port number as 2375.
4. Re-start SolidView to complete the client install.

\* The SolidView Network Server Tool was created using the RLM license manager obtained from Reprise ([www.reprisesoftware.com](http://www.reprisesoftware.com)).

## License Server Administration:

Open Internet Explorer to: <http://<servername>:5054/home.asp> or <http://<servername>:9000/home.asp> if you are accessing it from the server machine. (<SERVER> is the name of the machine where the License Server is installed)

Here you can restart the license server via the [Reread/Restart Server] button and check the SolidView license usage via the [Status] button.

## Example:

rlm admin - Reprise License Server Administration - Microsoft Internet Explorer provided by Solid Concepts Inc.

http://svserver01:5054/home.asp

### Reprise License Server Administration

Copyright (c) 2006-2007, Reprise Software, Inc. All Rights Reserved.

RLM License Server Administration, v6.0

This web interface is an integral part of the *rlm* server.

If *rlm* is started without any parameters, the web interface runs on port 9000. *rlm* can also be started with the `-nnows` option to disable this web interface. *rlm* can be started with the `-ws port#` option to specify another port number.

This tool allows you to perform status and administration functions on the RLM server. Choose a command from the list on the left-hand side of the window.

Reprise Software, Inc.  
1530 Meridian Ave  
Suite 290  
San Jose, CA 95125  
[www.reprisesoftware.com](http://www.reprisesoftware.com)  
[info@reprisesoftware.com](mailto:info@reprisesoftware.com)

RLM contains software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org>)  
Copyright (c) 1998-2003 The OpenSSL Project. All rights reserved.

Portions Copyright (c) 2005-2009 by Uniloc USA, Inc.

Webserver Copyright (c) 2006-2008 GoAhead Software, Inc. All Rights Reserved.  
<http://www.goahead.com/>

goahead  
**WEB SERVER**